

# REXYGEN Studio

## User guide

REX Controls s.r.o.

Version 2.50.8

2019-03-15

Plzeň (Pilsen), Czech Republic

# Contents

<b>1</b>	<b>Introduction</b>	<b>3</b>
1.1	Starting REXYGEN Studio . . . . .	3
1.2	Working Area . . . . .	3
1.3	Application Modes . . . . .	4
1.4	Main menu . . . . .	4
1.4.1	File . . . . .	4
1.4.2	Edit . . . . .	5
1.4.3	View . . . . .	6
1.4.4	Project . . . . .	6
1.4.5	Target . . . . .	7
1.4.6	Tools . . . . .	8
1.4.7	Settings . . . . .	8
1.4.8	Window . . . . .	8
1.4.9	Help . . . . .	8
<b>2</b>	<b>Function blocks</b>	<b>9</b>
2.1	Using Function Blocks . . . . .	9
2.1.1	Function Blocks Reference . . . . .	9
2.2	Block Properties . . . . .	10
2.3	Common Block Properties . . . . .	10
2.4	Connecting Blocks . . . . .	11
2.5	Persistent memory . . . . .	12
<b>3</b>	<b>Compile, Download and Diagnose Your Project</b>	<b>14</b>
3.1	Project Compilation . . . . .	14
3.2	Downloading Project . . . . .	14
3.3	License Activation . . . . .	15
3.4	Watch mode and Diagnostics . . . . .	16
3.4.1	Monitoring signals . . . . .	17
3.4.2	Viewing trends . . . . .	18
3.4.3	Viewing REXYGEN System Log . . . . .	18
3.4.4	Diagnostics . . . . .	19

<b>4</b>	<b>Creating a Library of Reusable Components</b>	<b>20</b>
4.1	Creation of a Subsystem . . . . .	21
4.2	Definition of Subsystem Mask . . . . .	21
4.3	Moving the Subsystem to a Library . . . . .	22
<b>5</b>	<b>Using User-Defined Libraries of Reusable Components</b>	<b>25</b>
5.1	Including a Library in Your Project . . . . .	25
5.2	Using Function Blocks From a Library . . . . .	25
5.3	Detaching a Library Reference . . . . .	26
<b>6</b>	<b>Supported Operating Systems</b>	<b>27</b>
<b>7</b>	<b>Keyboard Shortcuts</b>	<b>28</b>
<b>8</b>	<b>Other Important Features and Tools</b>	<b>30</b>
8.1	Human-Machine Interface . . . . .	30
8.2	REXYGEN HMI Designer . . . . .	30
8.3	REXYGEN Diagnostics . . . . .	30
	<b>Bibliography</b>	<b>33</b>

# Chapter 1

## Introduction

REXYGEN Studio is a graphical tool designed for a creation of real-time control algorithms with the support of a large function block library of the REXYGEN system [1]. A developer may utilize many function blocks from simple comparators and timers to advanced and specialized blocks designated for analog signal processing and regulation. There are various specialized regulators including PID regulators with automatic tuning of parameters. Any algorithm developed in the REXYGEN Studio may be instantly compiled and downloaded into arbitrary target device (Raspberry Pi, Linux IPC, WAGO PFC 100/200, Pigeon PLC, UniPi, etc.). After the algorithm is successfully compiled and downloaded to the target device, it is possible to switch REXYGEN Studio to a *Watch* mode in which all parameters and variables of all function blocks may be inspected or adjusted. A connection may be established locally or over Internet using standard protocol IPv4 or IPv6. A secure connection over SSL protocol is supported.

A detailed documentation for function block library may be opened at any time with the F1 key. The documentation is installed automatically in the default setup configuration and we advise not to uncheck it.

### 1.1 Starting REXYGEN Studio

The REXYGEN Studio development tool may be started without any parameters by double-clicking on its icon in a start menu of Windows. A main window of REXYGEN Studio consists of four main parts: a main menu (1), a toolbar (2), a working area (3) and a statusbar (4). There may be several files opened in the working area simultaneously. A name of opened and active file is shown in the title of REXYGEN Studio main window with an asterisk when there are unsaved modifications.

### 1.2 Working Area

A working area is a main area where windows with opened project files are placed. Files with function block diagram have a file name extension `.mdl`. A zoom operation is supported. Zoom in/out operations may be performed using a mouse wheel while keeping




Figure 1.1: Main Window of REXYGEN Studio

the **Ctrl** key pressed, clicking on those commands in the menu or in the toolbar and also by pressing the keys **F2** and **F3**.

## 1.3 Application Modes

The application provides two modes: a *Development* mode and a *Watch* mode. An algorithm is developed in the *Development* mode by drawing function block diagram on the canvas and by configuring function block parameters. The application may or may not be connected to a target device.

When connected to the target, the application may be switched to the *Watch* mode. In the *Watch* mode, the developed application can't be modified. Instead, the function block diagram serves as a diagnostic interface to the running algorithm. User may inspect all signals, parameters, trends and detailed diagnostics of the target.

## 1.4 Main menu

### 1.4.1 File

The File menu provides commands which are connected with files.

- *Start*: Opens a simple start dialog with multiple options that are available at the beginning of developing a control algorithms with REXYGEN Studio. The option is available only if no project is opened.

- *New*: Creates a new diagram file.
- *Open*: Opens an existing diagram file.
- *Close*: Closes an active file.
- *Close All*: Closes all opened files.
- *Save*: Saves an active file.
- *Save as*: Saves an active file under a new name.
- *Save all*: Saves all opened files.
- *Start with a Plain Project*: Creates and opens a new plain project.
- *Start from an Example Project*: Opens a dialog in which a user may select an example project that is provided within installation of REXYGEN. The selected project is copied into specified directory and opened. A user may start developing a new application by creating a new project from one of these examples.
- *Open Project from Target Device*: Storing of project source on target device is supported starting with REXYGEN version 2.50.4. If a project is stored on a target device, a user may upload it back to the computer and open it using this option.
- *Export*: Exports an active file to SVG format.
- *Set as Project Main File*: Selects an active file as a main project file.
- *Save Project as*: Duplicates an opened project into another directory, closes an opened project and re-opens it from the new location.
- *Print*: Prints an active file.
- *Print Preview*: Shows print preview before printing.
- *Print Setup*: Shows printing options.
- *Exit*: Closes all files and exits REXYGEN Studio.

#### 1.4.2 Edit

The Edit menu provides commands which are connected with objects and function blocks.

- *Undo*: Discards last editing operation.
- *Redo*: Restores discarded operation.
- *Select All*: Selects all object in an active window.
- *Cut*: Cuts selected objects.

- *Copy*: Copies selected objects into a clipboard.
- *Paste*: Pastes objects from a clipboard.
- *Properties*: Shows properties of selected objects.
- *Subsystem Mask*: Shows a mask of a subsystem (i.e. parametric dialog).
- *Look under Mask*: Opens a selected subsystem in a new window.
- *Create Subsystem*: Create a new subsystem from selected blocks.

### 1.4.3 View

The View menu provides commands and operations with REXYGEN Studio windows and working area.

- *Toolbar*: Show/hides the main toolbar.
- *Statusbar*: Shows/hides the statusbar.
- *Zoom In*: Zoom in within an active window.
- *Zoom Out*: Zoom out within an active window.
- *Zoom to 100 %*: Shows an active windows in default zoom scale.
- *Zoom to Fit*: Zoom an active window so that all object fit to the screen.
- *Block Library*: Opens a library with function blocks.
- *Compile window*: Shows a window with all messages from last compilation.

### 1.4.4 Project

The Project menu provides commands for project compilation, download, activating the *Watch* mode and watching signals.

- *Compile*: Compiles an active project into a binary configuration.
- *Compile and Download*: Compiles an active project and downloads the binary configuration into specified target if compilation is successful.
- *Activate Watch Mode*: Activates the *Watch* mode of REXYGEN Studio. A connection dialog is opened if REXYGEN Studio is not already connected to a target device. The *Watch* mode is indicated by a gray background of diagrams. A user may start monitoring signals after the *Watch* mode is activated. REXYGEN Studio remains connected to the target even if switched back to *Development* mode and all diagnostic data acquisition tasks continue in background.
- *Watch Selection*: Starts monitoring blocks that are selected.

- *Exclude from Watch*: Stops monitoring blocks that are selected.
- *Signal to Watch*: Shows a signal tree and advanced options for signal monitoring.
- *Check Parameter Changes*: User may check parameter changes made in the *Watch* mode anytime until the *Watch* mode is left. User may apply such changes back to the drawing or discards them.

#### 1.4.5 Target

The Target menu provides commands for communication with a target device, signal monitoring and detailed on-line diagnostics. Some commands are available only when a connection with a target device is established.

- *Connect*: Connects to a target device. The user is asked for target address and connection options. The application remains in *Development* mode.
- *Disconnect*: Disconnects from a target device and switches to *Development* mode.
- *Identify*: Shows target version and identification parameters of running project.
- *Show System log*: Downloads and shows messages from REXYGEN system log on a target device.
- *Configure System Log*: Shows a dialog for configuration of REXYGEN system log on a target device.
- *Diagnostics*: Shows a window with detailed diagnostics of a target device.
- *Backup*: Offers a way of creating a backup of a control algorithm that is stored on a target device. A user specifies a local file name into which the backup is stored. These components of control algorithm are stored into a backup: executive, human-machine interface and project source (if project source is stored on the target). A text file is created beside the backup that contains a detailed information about the content of the backup.
- *Restore*: Offers a way of restoring a control algorithm from a backup file to the target device. The operation is very similar to a download operation but a user may specify a file name of a backup.
- *Change password*: Shows a dialog in which a password of a current user may be changed.
- *Licensing*: Shows a dialog in which active licensed options are shown and a user may eventually add or modify licensing keys.
- *Web Interface*: Opens a web interface of a target device in a user's default web browser.

#### 1.4.6 Tools

The Tool menu is a shortcut for launching another tools available within REXYGEN.

- *REXYGEN Diagnostics*: Launches REXYGEN Diagnostics, a diagnostic tool for detailed inspection of running algorithm on a target device.
- *Cam Editor*: Launches an editor for cam profiles and curves.
- *SFC Editor*: Launches an editor for finite state machine. relevant function block is called *ATMT*.
- *REXYGEN HMI Designer*: Launches REXYGEN HMI Designer, a tool for a simple creation of web-based Human-Machine Interface (HMI).

#### 1.4.7 Settings

Dialogs with global and diagnostics options of REXYGEN Studio are accessible within the Settings menu.

#### 1.4.8 Window

The Window menu offers operations for arranging opened windows.

#### 1.4.9 Help

- *Function blocks manual*: Shows a detailed documentation for all function blocks that are available in the function block library of REXYGEN.
- *Examples*: Shows all available examples and templates.
- *Documentation*: Shows a list of documentation and manuals that are available for REXYGEN.
- *About REXYGEN Studio*: Shows a version information about the REXYGEN Studio.

## Chapter 2

# Function blocks

All function blocks in the function block library of REXYGEN are described in the reference manual [1].

### 2.1 Using Function Blocks

All function blocks that are available in REXYGEN and that may be added into a function block diagram are accessible within a function block library dialog that is shown from menu *View/Block Library* or by **Ctrl+L** shortcut.

By default, the library is in *Tree view* mode where the blocks are organized in sub-libraries. Their location is always denoted as **sublibrary/block**, e.g. **LOGIC/AND\_** for the logical **AND** block in the **LOGIC** sublibrary. Inside a sublibrary, the blocks are ordered in alphabetical order. It is also possible to switch the library to *List view* mode, where all the blocks are sorted alphabetically, regardless of the sublibrary they belong to. You may search for a particular function block by typing a name or a part of a name.

Blocks are added to the diagram by simple drag and drop operation. Both the symbol of a block and the name of a block may be dragged.

Another approach to adding function blocks is the so-called *Quick insert* feature. Just start typing the block name anywhere in the diagram and a list of matching function blocks will pop up. Clicking the function block of your choice will add it to the diagram.

#### 2.1.1 Function Blocks Reference

A detailed description of a selected block is invoked by the **F1** key or by selecting the *Help* from its context menu. A HTML documentation is opened by default. If the HTML documentation is not available (it was deselected during installation), REXYGEN Studio tries to open a PDF documentation and a user must scroll down to the corresponding block manually.




Figure 2.1: Function block library

## 2.2 Block Properties

All block properties can be modified using properties dialog. The dialog is invoked by double-clicking on the block in *Development* mode, by pressing the **Ctrl+E** shortcut or by selecting *Edit/Properties* from the menu. Dimensions of a block on the canvas may be changed with a mouse by first clicking on the block a then dragging any of highlighted corners. A block may be moved by mouse or by keyboard arrows while the block is selected. The block may be rotated using the **Ctrl+R** shortcut.

Properties that may be modified by the user:

- Block name,
- The *Parameters* tab: all parameters of the block,
- The *Runtime* tab: settings for behaviour of the block on the target device,
- The *Style* tab: size, font, color, background color, block orientation.

## 2.3 Common Block Properties

It is possible to modify common block properties by selecting several blocks at once. Such a multi-selection is performed by selecting arbitrary blocks one-by-one while keeping the




Figure 2.2: Adding function blocks via *Quick insert* feature

**Shift** key pressed or by selecting an arbitrary area with a mouse while the left mouse button is pressed.

Style of the selected blocks may be edited using the Properties dialog by pressing **Ctrl+E** or by selecting *Edit/Properties* from the menu after arbitrary blocks are selected. Only the *Style* tab is displayed. Other parameters must be edited manually.

## 2.4 Connecting Blocks

To build a control algorithm the blocks have to be put onto the drawing canvas of a diagram, their input and outputs connected and their parameters adjusted. It is expected that the user is familiar with the Function Block Diagram (FBD) graphical language for programmable logic controllers.

The blocks are connected by so-called *connection lines* or *links*. A *link* has always a single source and one or more sinks. A source may be any block output and a sink is any block input. It is not possible to connect two outputs together. A warning is shown during compilation when a source or sink of a *link* is not connected.

Links are created using the mouse by clicking on any input or output pin and holding the button pressed while moving towards another pin. A red dashed line is shown until the final pin is reached. When the final pin is reached, a green bold line is shown. The *line* becomes a standard *link* after the mouse button is released.

A branch may be created by right clicking on any point of an existing *link*. A *link* may be deleted by pressing the **Delete** key when the link is selected. A *link* may be disconnected from a pin by right clicking on the pin and selecting *Break/Disconnect line* from the context menu.




Figure 2.3: Block Properties

## 2.5 Persistent memory

REXYGEN supports permanent storage of function block parameters. Internal states of selected function blocks can be made persistent as well. Persistent memory performance is target platform specific. If the target platform does not have any supported persistent memory available, the permanent parameters will be stored to the `permem.dat` file by default (to the same directory as `exec.rex` is stored - `\rex\rexcore` on Linux targets or `C:\ProgramData\REXControls\REX_<version>\RexCore\` on Windows targets).

In order to store the function block parameters, the checkbox **Permanent** in block properties must be checked. All function block parameters and also internal states in selected blocks will be stored (excluding arrays).

The list of function blocks with persistent internal states follows:

- INTE:x
- SINT:x
- COUNT:cnt0

Default save period is 300 seconds.




Figure 2.4: Connection Between Blocks

The persistent memory can be reset or cleaned up using Download Dialog - see Fig. 3.1. Switch Download option in Download Dialog to **Expert** mode and choose between **Reset persistent memory** or **Cleanup persistent memory**. **Reset persistent memory** will replace entire persistent memory however **Cleanup persistent memory** will erase just the parameters which are not used any more.

Permanent storage file, it's size, location and save period can be changed using configuration file `rexcore.cfg`. More details can be found in the *RexCore User Guide*[2].

*Be aware that the block parameters will be overwritten with the ones stored in persistent memory immediately after swapping executives if the **Permanent** option is enabled for the function block.*

## Chapter 3

# Compile, Download and Diagnose Your Project

A project must be compiled and the resulting binary configuration has to be downloaded into the target device in order to put a control algorithm into operation. Both actions are performed directly from the REXYGEN Studio development tool.

### 3.1 Project Compilation

After an algorithm is designed, it is necessary to validate its structure, device configurations and block connections by *compilation*. The *compilation* results in a binary file called *binary configuration* which may be downloaded into a target device. The *binary configuration* is a platform/target independent file format with a **.rex** file name extension. The format of the *binary configuration* is optimized for fast-processing on a target device and has several consistency check mechanisms.

Warnings and errors may occur during a compilation. All warnings, errors and other various informational messages are print into the compiler console. A warning does not cause a termination of the compile process. But it should be observed carefully as it may probably indicate a problem that may lead into an unexpected behavior of the algorithm. All errors are treated as serious problems and cause a termination of the compiling process and no *binary configuration* is generated. All errors and warnings are indicated by theirs respective numbers and textual information message.

A *compilation* is started from the *Compiler* menu. A project is compiled by selecting *Compiler/Compile* from the menu, clicking on the icon on the toolbar or using the **F5** shortcut.

### 3.2 Downloading Project

A configuration is downloaded into the target device by selecting *Compiler/Compile and Download* from the menu, clicking on the icon on the toolbar or using the **F6** shortcut.

A compilation of a project into a *binary configuration* is always performed before it is downloaded into the target device to ensure consistency. If an error occurs during the compilation, a compiler window is shown and the download operation is not available. A user must fix all errors indicated by the compiler before proceeding with the download.




Figure 3.1: Project Compilation and Download Dialog

### 3.3 License Activation

Before a binary configuration may be downloaded and activated the target has to be properly licensed. For a permanent target operation a full target license can be obtained from [www.rexygen.com/pricing](http://www.rexygen.com/pricing). A DEMO license is available for experiments and development. A DEMO license may be obtained directly from the REXYGEN Studio application while connecting to unlicensed target. A user may also get the DEMO license from the web page of the REXYGEN Controls company.

An information dialog about licensing is shown while connecting to an unlicensed target (figure 3.2). A user has the following three options:

*Get DEMO Licence:* Select this option if you want to obtain a DEMO licence directly by filling-in name and email address to which a licensing key is sent (figure 3.3).

*I already have a licence:* Select this option if you already have a valid licence and you want to submit a licensing key into target device (figure 3.4).




Figure 3.2: Missing License Notification

*Connect anyways:* Select this option if you want to continue without licensing the target. But be aware that most of its functionality is not available without active licence.

### 3.4 Watch mode and Diagnostics

A comprehensive diagnostic tool is integrated directly into the REXYGEN Studio development tool. Before using the diagnostic tool, a binary configuration must be successfully downloaded into the target device. For information about downloading a binary configuration into the target device see the section 3.2.

A diagnostic tool in REXYGEN Studio may be used only when there is an active connection with the target device established. The connection is established by clicking on *Target/Connect* from the menu, clicking on the icon on the toolbar or using the F7 shortcut. The connection may also be established after a binary configuration is downloaded into the target device and a dialog is shown in which a user is asked if the connection with the target should be preserved and the so-called *Watch mode* should be activated.

A *Watch mode* is indicated by a gray background of all windows with function block diagrams. It is not possible to add, delete or move function block or connections between blocks in the *Watch mode*. Instead, a user may inspect and adjust signals of all block inputs, outputs and parameters and observe all signal values in real-time with a refresh period that may be adjusted in the *Settings/Diagnosics Options* dialog and which is one second by default.




Figure 3.3: DEMO License Dialog




Figure 3.4: Insertion of a Licensing Key

### 3.4.1 Monitoring signals

It would be inefficient and bandwidth-consuming if all signals were monitored immediately when the *Watch* mode is activated. For that reason, only the **DISPLAY** blocks are monitored automatically. A user has to switch other function blocks into the so-called *Monitoring State* if signals of a particular block should be monitored.

When a block is in the *Monitoring State*, all input and output values are displayed at the corresponding pin of the monitored block. A block is added to the *Monitoring State* by selecting *Project/Watch Selection* from the menu or using the **Ctrl+W** shortcut. A block is removed from the *Monitoring State* by selecting *Project/Exclude from Watch* from the menu or using the **Ctrl+Shift+W** shortcut.

The values of parameters are shown in a floating yellow window when a user positions the mouse cursor over a function block. Parameters may also be inspected and adjusted from the on-line block properties dialog that is invoked by double-click or by pressing **Ctrl+E**. Be careful when modifying the values of parameters as changes are immediately committed to the target when the *OK* or *Apply* button is selected.

A dialog that allows to transfer all changes to the parameters made in the *Watch* mode back to the drawing is displayed before exiting *Watch* mode. A user may accept or discard changes to all parameters individually. This simplifies an effort to keep a project synchronized with the running configuration.

A user should always observe a right part of the status bar where a state of the

connection with the target device is indicated. A green color indicates that connection is active and the data is communicated periodically without any errors. A red color indicates that the connection with the target device has been unexpectedly closed or an error occurred during the data exchange.




Figure 3.5: Monitoring and Diagnostics in the *Watch* Mode

### 3.4.2 Viewing trends

The blocks **TRND** and **TRNDV** are available in **REXYGEN** to monitor signals over a period of time. The **TRND** allows to save up to 4 signals and the **TRNDV** allows to save up to 64 signals into the RAM memory of the target device. The samples are stored synchronously during a task execution. This allows to store and observe very fast processes without losing a single sample.

The diagnostic tool of the **REXYGEN** Studio makes it possible to show all the data stored in the memory of the **TRND** block in the *Watch* mode. To show a windows with all data signals shown in a graphical trend simply double-click on a **TRND** block while the **REXYGEN** Studio is in the *Watch* mode. A data may be zoomed, a scale and a range of both axes may be changed and the data may also be exported do a **CSV** file from the window.

### 3.4.3 Viewing REXYGEN System Log

A system log with errors, warnings and other info messages with timestamps is present on every target device. A user may display a content of the system log directly from

the REXYGEN Studio selecting *Target/Show System Log* from the menu or by clicking on the icon on the toolbar. A user may browse all messages, filter the content or export selected/all items to a CSV file.

The types and severities of messages that are written to the REXYGEN System log may be configured by selecting *Target/Configure System Log* from the menu. The *Safe print flags to the target* option must be selected if it is required to store the configuration of the system log permanently on the target device. A last saved configuration is loaded during the next system boot if the option remains unselected.

#### **3.4.4 Diagnostics**

A detailed diagnostics tool may be launched by clicking on *Target/Diagnostics* from the menu or by clicking on the icon on the toolbar.

The diagnostic tool window is closed automatically when REXYGEN Studio disconnects from the target device.

## Chapter 4

# Creating a Library of Reusable Components

In REXYGEN, creating reusable components is based on using the so-called subsystems. A subsystem is a container for a group of function blocks and their connections, which then appear as a single block. Nesting of subsystems is allowed, i.e. a subsystem can include additional subsystems. Any subsystem can be turned into a reusable component.

A reusable component can be created in 3 steps:

1. Creation of a subsystem
2. Definition of subsystem mask
3. Moving the subsystem to a library




Figure 4.1: Subsystem – A container for a group of function blocks

## 4.1 Creation of a Subsystem

There are two possible ways of creating a subsystem in REXYGEN Studio:

- Copy the **SubSystem** block from the **INOUT** library to the given diagram (.mdl file). Enter the subsystem by a double-click. Duplicate **Inport** and **Outport** blocks as needed. Insert function blocks as needed. Route the signals from Inports through function blocks to Outports. Rename Inports and Outports as needed.
- Select a group of blocks and use the **Create subsystem** command (in menu *Edit→Create subsystem*). The selected blocks are then replaced a subsystem block, which contains all the original blocks and **Inport** and **Outport** blocks for signals crossing the subsystem boundary.

The resulting subsystem contains function blocks and their connections as shown in Figure 4.1.

## 4.2 Definition of Subsystem Mask

A typical requirement for a subsystem is to have parameters just like a standard function block to allow parametrization of its functionality.

For this purpose the so-called *subsystem mask* can be defined. The mask defines parameters whose values can be used inside the subsystem. Each parameter also has a description of its meaning. To create a subsystem mask, select one subsystem block and go to menu *Edit→Subsystem Mask*. A dialog appears (see Figure 4.2) and you can define parameters and the corresponding descriptions.

Once a mask is created, the subsystem acts just like any other block – double-click it to open the *Block properties* dialog. You can see the dialog contains the parameters defined in the subsystem mask (Figure 4.3).

Now you need to edit the internals of a masked subsystem. Select it and go to menu *Edit→Look under Mask*.

The function blocks inside a masked subsystem must be configured to accept the values from the mask. To do so, open the *Block properties* dialog of individual function blocks, tick the **Masked** checkbox and select the corresponding mask parameter (Figure 4.4).

The internals of the finished masked subsystem is shown in Figure 4.5.

In the end you are able to use the subsystem just like any other function block and you'll find yourself configuring its behavior using the *Block properties* dialog. If everything works well, you might never go inside the subsystem again. If you need to debug your block or add new features/inputs/outputs, you can always *Look under Mask* and do what's needed.

Please refer to example project 0101-02 which demonstrates the use of subsystems. The example projects are a standard part of REXYGEN Studio.




Figure 4.2: Subsystem – Definition of mask parameters

### 4.3 Moving the Subsystem to a Library

Once you have your subsystem working, with or without its mask, chances are that you'll want to use it in multiple tasks or projects. For such a purpose, you'll create your own Library of subsystems. Your very own and problem-oriented library of reusable components.

To do so, create a new file in REXYGEN Studio and go to menu *File*→*File Type* and change it to a *Library*.

Now you can fill your library with as many subsystems as you like. Just drag&drop subsystems to the library.

Afterwards save the library to the project folder. It is recommended to include 'library' in the filename so you can easily recognize it later. The extension is *.mdl*, just like in other REXYGEN Studio files.

Once you close the library and open it again, you'll notice its background is light blue and the library is in read-only mode. If you want to make some changes in the library, go to menu *File*→*Unlock Library*. This will make the library editable and you can do what is needed. Keep in mind that the changes you make will be applied to all files and projects referencing the library (we'll get to that in chapter 5).

*Note 1: The subsystems in the library can be standalone or they can be built on top of other subsystems from the same or from other user libraries.*

*Note 2: All files and projects referencing components in the library refer to the file-*




Figure 4.3: Subsystem with mask – User-defined parameters

*name of the library. Renaming an existing library will lead to breaking references in all places. IT IS HIGHLY RECOMMENDED NOT TO RENAME A LIBRARY once you have started using its contents in your projects.*




Figure 4.4: Block properties dialog – Accept parameters from subsystem mask




Figure 4.5: Subsystem with mask – Internals of the finished subsystem

## Chapter 5

# Using User-Defined Libraries of Reusable Components

### 5.1 Including a Library in Your Project

When you have your own library ready (or when you want to use a 3rd party library of function blocks), you must include the library in your project. There are three ways to do so:

1. Place the library (.mdl file) in the project folder.
2. Include the **PROJECT** block in the project main file and configure its **LibraryPath** to point to the folder with the library. The path can be absolute or relative to the project folder.
3. Define a global path to libraries in *Settings*→*Program Options*. The path must be absolute.

### 5.2 Using Function Blocks From a Library

To use a function block from a library in your project, open the library like any other file in REXYGEN Studio and drag&drop function blocks to your project. This creates the so-called references to library blocks, which you can use just like all the native blocks of REXYGEN.

A library reference can be distinguished from a standard subsystem by the style of the upper border.

The difference from a standard subsystem (and the greatest benefit and the main purpose of a library reference) is that the content of the subsystem is given by the library. Therefore if you or anyone else update the library, the changes will be distributed to all subsystems referencing the library. To apply the changes in a project, you'll need to open the project in REXYGEN Studio.




Figure 5.1: Standard subsystem vs. Library reference

Please refer to example project 0101-03 which demonstrates the use of user-defined libraries. The example projects are a standard part of REXYGEN Studio.

*Note: All files and projects referencing components in the library refer to the filename of the library. Renaming an existing library will lead to breaking references in all places. IT IS HIGHLY RECOMMENDED NOT TO RENAME A LIBRARY once you have started using its contents in your projects.*

### 5.3 Detaching a Library Reference

In some cases you might need to break the link between the library reference and its origin. WARNING! This process is IRREVERSIBLE. This will turn the library subsystem into a standard subsystem. To do so, select the block and go to menu *Edit*→*Break Library Link*. You'll immediately notice that the upper border of the block is now a thick full line, indicating that the subsystem is no longer dependent on the library.

## Chapter 6

# Supported Operating Systems

All 32-bit and 64-bit Windows 7 and later operating systems are supported by development tools of REXYGEN. Windows Vista may also work but no guarantee nor support is provided for this version.

It is also possible to run all development tools on macOS or GNU/Linux on a 32-bit or 64-bit x86 platform using *Wine* from [www.winehq.org](http://www.winehq.org). Although we test the development tools in *Wine* regularly, please note that this is meant for experienced users and only a very limited support is provided. You should have at least version 2.0 of *Wine* installed. The *corefonts* package must be installed using the command `winetricks corefonts`.

## Chapter 7

# Keyboard Shortcuts

Keyboard shortcut	Function (as presented in the menu)
CTRL+N	New File
CTRL+O	Open File
CTRL+S	Save File
CTRL+P	Print
CTRL+SHIFT+S	Save as
CTRL+Z	Undo
CTRL+Y	Redo
CTRL+A	Select All
CTRL+X	Cut
CTRL+C	Copy
CTRL+V	Paste
CTRL+R	Rotate Block Clockwise
CTRL+SHIFT+R	Rotate Block Counterclockwise
CTRL+F	Find Function Block
CTRL+E	Properties
CTRL+M	Subsystem Mask
CTRL+U	Look under Mask
CTRL+G	Create Subsystem
CTRL+L	Block Library
F2	Zoom In
F3	Zoom Out
F4	Zoom Default
F1	Help
F5	Compile
F6	Compile and Download
F7	Connect
F8	Disconnect
F9	Activate/Deactivate <i>Watch</i> Mode
CTRL+W	Watch Selection
CTRL+SHIFT+W	Exclude from Watch

Table 7.1: Keyboard shortcuts in REXYGEN Studio

## Chapter 8

# Other Important Features and Tools

### 8.1 Human-Machine Interface

Each target device running the **RexCore** contains an integrated webserver. The webserver and the webpages it provides may act as a Human-Machine Interface (HMI) for your application. The web interface with HMI may be opened from **REXYGEN Studio** by selecting *Target/Web Interface* in the menu.

Please refer to documentation of the **HMI** block in [1] on including the HMI in your project. All types of HMI supported by **REXYGEN** are described in [3].

### 8.2 REXYGEN HMI Designer

One of the approaches to creating a HMI for your application is to use the **REXYGEN HMI Designer**.

The **REXYGEN HMI Designer** may be started directly from the **REXYGEN Studio** by clicking on *Tools/REXYGEN HMI Designer* from the menu or by clicking on the icon on the toolbar. See [4] and [3] for details on using the **REXYGEN HMI Designer**.

### 8.3 REXYGEN Diagnostics

**REXYGEN Diagnostics** provides all the functionality which is available from the diagnostic tool in **REXYGEN Studio**, only as a stand-alone application.

**REXYGEN Diagnostics** may be started directly from **REXYGEN Studio** by clicking on *Tools/REXYGEN Diagnostics* from the menu or by clicking on the icon in the toolbar.




Figure 8.1: WebWatch – Monitoring signals in a web browser

# List of Figures

1.1	Main Window of REXYGEN Studio . . . . .	4
2.1	Function block library . . . . .	10
2.2	Adding function blocks via <i>Quick insert</i> feature . . . . .	11
2.3	Block Properties . . . . .	12
2.4	Connection Between Blocks . . . . .	13
3.1	Project Compilation and Download Dialog . . . . .	15
3.2	Missing License Notification . . . . .	16
3.3	DEMO License Dialog . . . . .	17
3.4	Insertion of a Licensing Key . . . . .	17
3.5	Monitoring and Diagnostics in the <i>Watch</i> Mode . . . . .	18
4.1	Subsystem – A container for a group of function blocks . . . . .	20
4.2	Subsystem – Definition of mask parameters . . . . .	22
4.3	Subsystem with mask – User-defined parameters . . . . .	23
4.4	Block properties dialog – Accept parameters from subsystem mask . . . . .	24
4.5	Subsystem with mask – Internals of the finished subsystem . . . . .	24
5.1	Standard subsystem vs. Library reference . . . . .	26
8.1	WebWatch – Monitoring signals in a web browser . . . . .	31

# Bibliography

- [1] REX Controls s.r.o.. *Function blocks of REXYGEN – reference manual*, 2018. [→](#).
- [2] REX Controls s.r.o.. *RexCore – User manual*, 2018. [→](#).
- [3] REX Controls s.r.o.. *REXYGEN HMI – User manual*, 2018. [→](#).
- [4] REX Controls s.r.o.. *Getting started with REXYGEN*, 2018. [→](#).